### NATURAL RESOURCES CONSERVATION SERVICE CONSERVATION PRACTICE STANDARD

### **DEEP TILLAGE** (ACRE)

### **CODE 324**

### **DEFINITION**

Performing tillage operations below the normal tillage depth to modify the physical or chemical properties of a soil.

### **PURPOSES**

This practice may be applied as part of a conservation management system to support one or more of the following:

- Fracture restrictive soil layers.
- Bury or mix soil deposits from wind or water erosion or flood overwash.
- Reduce concentration of soil contaminants, which inhibit plant growth.

### **CONDITIONS WHERE PRACTICE APPLIES**

This practice applies to land having adverse soil conditions which inhibit plant growth, such as compacted layers formed by field operations, restrictive layers such as claypans, overwash or deposits from wind and water erosion or flooding, or contaminants in the root zone.

This standard includes tillage operations commonly referred to as deep plowing, subsoiling, ripping, or row-till, performed from time to time below the normal tillage depth.

### **CRITERIA**

### **General Criteria Applicable to All Purposes**

Deep tillage operations shall be performed when soil moisture is less than 30 percent of field capacity, according to the "feel test" or other

acceptable method, at the maximum depth to which the tillage will be done.

When slopes exceed 5 percent, deep tillage shall be completed across the slope to reduce potential for water erosion.

Tillage shall be completed in a manner that maintains adequate amounts of residue on the soil surface to meet resource concerns.

## Additional Criteria to Fracture Restrictive Soil Layers

Tillage equipment such as chisels, subsoilers, bent-leg subsoilers, or rippers, with the ability to reach the required depth shall be used.

The depth of tillage shall be a minimum of one inch deeper than the depth of the restrictive layer. Tillage depth should be set carefully and periodically checked to maintain this working depth.

Complete fracturing of the restrictive layer is not required. **However**, the fractured zone, as a minimum, shall be sufficient to permit root penetration below the restrictive soil layer. The fractured zone does not need to extend to the row middles and should be limited to the area near the rows [in the case of crops broadcast-planted or drilled in narrow rows (less than 15 inches), the fractured zone may be disrupted completely].

# Additional Criteria to Bury or Mix Soil Deposits from Wind and Water Erosion or Flood Overwash

Tillage equipment such as moldboard plows disk plows or chisels with twisted points, with the ability to reach the required depth shall be used.

> NRCS, MT April, 2002

Conservation practice standards are reviewed periodically and updated if needed. To obtain the current version of this standard contact the Natural Resources Conservation Service.

#### 324-2

The tillage operation shall uniformly mix soil 6" or 2 times (2 X) the depth of overwash, whichever is deeper, to achieve a desired available waterholding capacity (AWC) and to break the hydrologic barrier caused by overwash layer.

### <u>Additional Criteria to Reduce Concentration of</u> Soil Contaminants Which Inhibit Plant Growth

Tillage equipment such as moldboard plows, disk plows or chisels with twisted points, with the ability to reach the required depth shall be used.

The tillage operation shall mix a sufficient amount of uncontaminated soil with the contaminated material so that the concentration of the contaminant is below the crop tolerance level. Crop tolerance levels shall be established in accordance with Land Grant University guidance and recommendations.

The soil contaminant shall be uniformly distributed throughout the deep tilled layer.

### **CONSIDERATIONS**

Where restrictive layers are a concern, the effects of this practice can be enhanced by including deep rooted as well as fibrous rooted crops in the rotation that are able to extend to and penetrate the restrictive layer.

Varying the depth of tillage operations may reduce the frequency of utilizing this practice.

Research on numerous crops has shown that tillage conducted excessively deeper than the compacted layer does not promote increased yields, requires excessive amounts of tillage energy, and promotes future compaction from nearby vehicle traffic.

Reduce or control equipment traffic during periods when soils are prone to compaction and formation of tillage pans.

When infertile flood overwash is mixed with the pre-flood soil profile, the soil rebuilding process can be enhanced by additions of organic matter, such as manure or cover crops utilized as green manure. Crop rotations, tillage and planting systems, which maintain high levels of crop residues, such as no-till, can also accelerate this process.

Where the flood overwash layer is too thick to effectively mix with the pre-flood soil profile, redistribution of the overwash layer by smoothing or removal may be necessary. Generally, no more than about 6 inches of overwash can be uniformly mixed into the soil profile using commonly available equipment. Specialized equipment may be necessary where greater depths of overwash are to be incorporated.

Where unfavorable soil materials such as high sodium, calcium, gypsum or other undesirable materials, are within anticipated deep tillage depth and would be brought to the surface by deep tillage operations, this practice should not be applied.

Transport of sediment-borne pollutant(s) offsite can be reduced when this practice is used in a conservation management system, by reducing the concentration of pollutants in the surface layer.

To help reduce compaction, it is desirable to conduct normal tillage operations when soil moisture is less than 50 percent of field capacity. When possible, harvest operations should be avoided when soil moisture is greater than 50 percent of field capacity. Field harvest haul traffic should be limited to end rows or haul roads. Compacted regions between crop rows that are not fractured can assist in supporting vehicle traffic, limiting rutting and soil compaction beneath the row.

If application of this practice will impact cultural resources (Archaeological, historic, historic landscape, or traditional cultural properties), follow NRCS national policy and State operating procedures for considering cultural resources.

Consider using points from 2–4 inches in width for best results when breaking restrictive layers. Although spacing will depend greatly on local conditions, chisel points from 12–24 inches apart are optimum for breaking restrictive layers to 18 inches.

### PLANS AND SPECIFICATIONS

Specifications for establishment and operation of this practice shall be prepared for each field or treatment unit according to the Criteria, Considerations and Operations & Maintenance described in this standard.

A deep tillage establishment plan shall include the following information and documentation:

- Location map—field numbers and a map or sketch of the area to be established.
- 2. Measured acres.
- 3. Date practice scheduled and applied.
- 4. Operation and maintenance requirements.
- 5. Soil map unit information along with pertinent soil details.
- 6. Field slopes (%).
- 7. Measured depth of compacted or restrictive layer.
- 8. Measured depth of soil deposits or overwash (if applicable).

- 9. RUSLE water erosion prediction for each field practice will be implemented.
- 10. Deep Tillage point spacing.
- 11. Deep Tillage depth.
- 12. The Deep Tillage Specification and Jobsheet.

### **OPERATION AND MAINTENANCE**

Deep tillage for reduction of soil compaction shall be performed whenever compaction reoccurs.

When deep tillage has been performed to reduce the concentration of soil contaminates, the contaminate levels in the root zone shall be monitored to assist with determining when or if treatment will be reapplied.